

RTD31	RTD32	THD01	DCV31	DCV32	TRQ31
calculated, DigIn, DigOut, OHMS, Temp/RTD	calculated, DigIn, DigOut, OHMS, Temp/RTD	calculated, dewpoint, Humidity, OHMS, Temp/Thermst, VDC	calculated, DigIn, DigOut, OHMS, Temp/Thermst	calculated, DigIn, DigOut, OHMS, Temp/Thermst	calculated, DigIn, DigOut, Horse-power, RPM, Strain, Torque, Weight, VDC

:Config:Comm:EthernetID?

Query Ethernet Address

Allows the user to determine the unique Ethernet ID number hard-coded in instrument firmware.

Query:

:Config:Comm:EthernetID? Responds with the Ethernet ID number

:Config:Comm:ENet

Set Ethernet IP Address

Sets up Ethernet IP Address

:Config:Comm:ENet <IPAddress>

<IPAddress>

The Internet protocol address is specified by your network system administrator. The address is in string format (xxx.xxx.xxx.xxx) . This parameter is not required if Boot P is running on the network server. Default is 0.0.0.0

Query:

:Config:Comm:ENet? Responds with the user-entered IP address. Format of the response is identical to the format of the command shown above.

See also: Communication Section

:Config:Comm:Local Setup Local Communications Port

Sets up parameters for the local communications port.

```
:Config:Comm:Local <9600|1200|2400|4800|19200>
                    <CR|CRLF|LF|none>
                    <XonXoff|none>
```

~~<9600|1200|2400|4800|19200>~~ Sets baud rate. Default is 9600.

<CR|CRLF|LF|none> Sets line terminator. Default is CR.

<XonXoff|none> Sets flow control to Xon/Xoff or none. Default is XonXoff.

Query:

:Config:Comm:Local? Responds with configuration parameters for the local communications port. Format of the response is identical to the format of the command shown above.

See also: Communication Section

:Config:Comm:RS232 Setup RS232 Communications

Sets up RS232 communications parameters

```
:Config:Comm:RS232 <9600|1200|2400|4800|19200>
                    <CR|CRLF|LF|none>
                    <XonXoff|none>
```

~~<9600|1200|2400|4800|19200>~~ Sets baud rate. Default is 9600.

<CR|CRLF|LF|none> Sets line terminator. Default is CR.

<none|XonXoff> Sets flow control to Xon/Xoff or none. Default is XonXoff.

Query:

:Config:Comm:RS232? Responds with configuration parameters for RS232 communication. Format of the response is identical to the format of the command shown above.

See also: Communication Section

Example:

```
:config:comm:RS232 19200 CRLF none
```

:Config:Comm:RS422 Setup RS422 Communications

Sets up RS422 communications parameters

```
:Config:Comm:RS422 <9600|1200|2400|4800|19200>
                   <CR|CRLF|LF|none>
                   <XonXoff|none>
```

~~<9600|1200|2400|4800|19200>~~ Sets baud rate. Default is 9600.

<CR|CRLF|LF|none> Sets line terminator. Default is CR.

<XonXoff|none> Sets flow control to Xon/Xoff or none. Default is XonXoff.

Query:

:Config:Comm:RS422? Responds with configuration for RS422 communications. Response is identical to the format of the command shown above.

See also: Communication Section

:Config:Comm:RS485 Setup RS485 Communications

Sets up RS485 communications parameters

```
:Config:Comm:RS485 <9600|1200|2400|4800|19200>
                   <CR|CRLF|LF|none> <address>
```

~~<9600|1200|2400|4800|19200>~~ Sets baud rate. Default is 9600.

<CR|CRLF|LF|none> Sets line terminator. Default is CR.

<address> Sets address to any single, printable ASCII character. Default is 0 (zero).

Query:

:Config:Comm:RS485? Responds with configuration of RS485 communications. Format of the response is identical to the format of the command shown above.

See also: Communication Section